

# VP 729 Command Sets

## History

No	Issue Date	Version	Description	Firmware
1	2008/3/19	V1.0	First release	
2	2008/6/24	V1.1	<ol style="list-style-type: none"> <li>1. Add only those that we can't simulate their pressing using other commands of the protocol, such as MENU, Up, Down, Left, Right.</li> <li>2. Query the status of the input (valid or invalid input, and (if valid) can provide. details such as the standard or resolution.</li> <li>3. Update command with Layer C spec.</li> <li>4. Modify Command format example</li> <li>5. Add two commands to get input status.</li> </ol>	
3	2008/9/9	V1.2	<ol style="list-style-type: none"> <li>1 Update parameter range</li> <li>2 Add Output Resolution – 1920x1080@60Hz</li> <li>3 Gray unavailable command</li> <li>4 command update for Geometry Diagonal Projection</li> <li>5 Add error code</li> </ol>	
4	2008/11/25	V1.3	<ol style="list-style-type: none"> <li>1. Add command for Input/Output mode custom</li> <li>2. Add command for PIP Custom</li> <li>3. Add command for Aspect Ratio Custom</li> <li>4. Remove USB PIP Source</li> <li>5. Change Aspect Ratio name: Anamorphic -&gt; Follow Output, Native -&gt; Follow Input</li> </ol>	
5	2009/1/23	V1.4	<ol style="list-style-type: none"> <li>1. Change parameter range of Input V-position.</li> </ol>	
6	2009/04/06	V1.5	<ol style="list-style-type: none"> <li>1. Add custom1~4 in Output Resolution.</li> <li>2. Add custom1~4 in Advance Output Mode: Apply.</li> <li>3. Add Volume up</li> <li>4. Add Volume down.</li> </ol>	VTB1.05

			<ul style="list-style-type: none"> <li>5. Add 1280x720@60Hz in Output Resolution.</li> <li>6. Cancel HDMI output device, add HDCP setting</li> <li>7. Add Custom Input1~4 in Advanced Input Mode</li> <li>8. Add Custom Output1~4 in Advanced Output Mode</li> <li>9. Modify Apply to Save in Advanced Input Mode.</li> <li>10. Modify Apply to Save in Advanced Output Mode.</li> </ul>	
7	2009/05/27	V1.6	<ul style="list-style-type: none"> <li>1. Update Main/PIP input status for new 1280x800 input mode</li> <li>2. Add command "Y 0 48 111"/"Y 0 48 -111" for VOLUME UP/DOWN</li> <li><del>3. Remove command 133, 134</del></li> <li>4. Rename Aspect Ratio Standard -&gt; Best Fit</li> </ul>	VTB1.07
8	2009/7/10	V1.7	<ul style="list-style-type: none"> <li>1. modify Y 1 103 98: No Input detected</li> <li>2. modify Y 1 103 99: other</li> </ul>	
9	2009/7/14	V1.8	<ul style="list-style-type: none"> <li>1. remove USB audio : HDMI1, HDMI2</li> </ul>	
10	2009/7/27	V1.9	<ul style="list-style-type: none"> <li>1. Update the range of Input H-Position, Input V-Position and Input Frequency</li> </ul>	VTB1.09
11	2009/9/2	V2.0	<ul style="list-style-type: none"> <li>1. add command set for Overscan</li> <li>2. add command set for Fast mode</li> <li>3. add command set to select on or off for auto image function when source switching.</li> <li>4. add command set for Slideshow</li> </ul>	VTB1.11
12	2009/10/21	V2.1	<ul style="list-style-type: none"> <li>1. modify Y 1 104 98: No Input detected</li> <li>2. modify Y 1 104 99: other</li> </ul>	VTB1.12
13	2010/2/5	V2.2	<ul style="list-style-type: none"> <li>1. Add input mode for Main input status (Command = 103) / PIP input status (Command = 104) 1680x1050@60 (R) 1366x768@60 1366x768@60 (R)</li> <li>2. Add Mode3 Command (Command = 147)</li> </ul>	VTB1.14
14	2010/3/29	V2.3	<ul style="list-style-type: none"> <li>1. Command is modified to match with FW</li> </ul>	VTB1.15

15	2010/12/16	V2.4	1. Add HDMI Switch Behavior Command (Function = 148 / 149)	VTB1.20
16	2011/03/22	V2.5	1. Add HDMI1 Audio Input (Command = 150) Add HDMI2 Audio Input (Command = 151) 2. Add Custom Output Read HDMI EDID Prefer Timing (Command = 152) 3. Add HDMI1 Input HDCP On/Off (Command = 153) Add HDMI2 Input HDCP On/Off (Command = 154) 4. Add Output Mode (Command = 25) 33: 480P@59.94Hz 34: 720P@59.94Hz 35: 1080i@59.94Hz 36: 1080P@23.98Hz 37: 1080P@29.97Hz 38: 1080P@59.94Hz	VTB1.21
17	2012/03/15	V2.6	1. Fix Example Example function code from 0 change to 1 2. Function 148, 149 『Switch Behavior』 change to 『Hot Plug』	VTB 1.24

**\*Notice:**

1. The RS-232 command is for VP-728 and VP-729 only.
2. The blue highlight  means the latest update
3. The yellow highlight  means the deleted item.

## 1 Serial Configuration:

- Baud rate : 9600(Bits per second)
- Data bits : 8bits
- Parity : None
- Stop bits : 1bit

## 2 Command Format:

### 2.1 Communication confirm

Send	CR
Reply	CRLF>

### 2.2 Set Command

Send	YΔControl_TypeΔFunctionΔParamCR
Reply	ZΔControl_TypeΔFunctionΔParamCRLF>

### 2.3 Get Command

Send	YΔControl_TypeΔFunctionCR
Reply	ZΔControl_TypeΔFunctionΔParamCRLF>

### 2.4 Example: set Input 1 Source Type to Component

Send	YΔ0Δ1Δ0CR
Reply	ZΔ0Δ1Δ0CRLF>

### 2.5 Example: get current Input 1 Source Type


Send	YΔ1Δ1CR
Reply	ZΔ1Δ1Δ0CRLF >

### 2.6 Δ : ASCII Code 0x20


### 2.7 CR : Ascii Code 0x0D

### 2.8 CRLF : Ascii Code 0x0D+0x0A

## 2.9 Communication flow



## 2.10 Communication limitation



### 3 Command List:

Control Type		Function	Parameter	Description
Set	Get			
0	1	0	0: Input 1 1: Input 2 2: Input 3 3: Input 4 4: VGA 1 5: VGA 2 6: HDMI 1 7: HDMI 2 8: USB	Input Source
0	1	1	0: Component 1: YC 2: Video	Input 1 Source Type
0	1	2	0: Component 1: YC 2: Video	Input 2 Source Type
0	1	3	0: Component 1: YC 2: Video	Input 3 Source Type
0	1	4	0: Component 1: YC 2: Video	Input 4 Source Type
0	1	5	0: Auto 1: RGB 2: YUV	Input Color Format

Control Type		Function	Parameter	Description
Set	Get			
0	1	6	0: Auto 1: NTSC 2: PAL 3: PAL-M 4: PAL-N 5: NTSC 4.43 6: SECAM 7: PAL-60	Input Video Standard
0	1	7	1 ~ N	Input H-Position, N: changed with different input mode
0	1	8	2 ~ N	Input H-Position, N: changed with different input mode
0	1	9	0 ~ N	Input H-Position, N: changed with different input mode
0	1	10	0 ~ 31	Input Phase
0	-	11	n/a	Input Auto Image
0	1	12	0~100	Picture Brightness
0	1	13	0~100	Picture Contrast
0	1	14	0~100	Picture Color
0	1	15	0~360	Picture Hue
0	1	16	0~100	Picture Sharpness
0	1	17	0: Gamma 1 1: Gamma 2 2: Gamma 3 3: Gamma 4	Picture Output Gamma

Control Type		Function	Parameter	Description
Set	Get			
			4: Gamma 5	
0	1	18	0: Auto 1: Video 2: Film	Picture Film Mode
0	1	19	0: Off 1: Low 2: Medium 3: High	Picture Temporal NR
0	1	20	0: Off 1: Low 2: Medium 3: High	Picture Mosquito NR
0	1	21	0: Off 1: On	Picture Block NR
0	1	22	0: Off 1: Low 2: Medium 3: High	Picture Detail Enhancement
0	1	23	0: Off 1: Low 2: High	Picture Luma Transition Enhance



Control Type		Function	Parameter	Description
Set	Get			
0	1	24	0: Off 1: Low 2: High	Picture Chroma Transition Enhance
0	1	25	0 : Native HDMI 1 : 640x480@60Hz 2 : 640x480@75Hz 3 : 800x600@50Hz 4 : 800x600@60Hz 5 : 800x600@75Hz 6 : 1024x768@50Hz 7 : 1024x768@60Hz 8 : 1024x768@75Hz 9 : 1280x768@50Hz 10: 1280x768@60Hz 11: 1280x720@60Hz 12: 1280x800@60Hz 13: 1280x1024@50Hz 14: 1280x1024@60Hz 15: 1280x1024@75Hz 16: 1366x768@50Hz 17: 1366x768@60Hz 18: 1400x1050@50Hz 19: 1400x1050@60Hz 20: 1600x1200@50Hz 21: 1600x1200@60Hz	Output Resolution

Control Type		Function	Parameter	Description
Set	Get			
			22: 1680x1050@60Hz 23: 1920x1080@60Hz 24: 1920x1200@60Hz 25: 480p@60Hz 26: 576p@60Hz 27: 720p@50Hz 28: 720p@60Hz 29: 1080i@50Hz 30: 1080i@60Hz 31: 1080p@50Hz 32: 1080p@60Hz 33: 480P@59.94Hz 34: 720P@59.94Hz 35: 1080i@59.94Hz 36: 1080P@23.98Hz 37: 1080P@29.97Hz 38: 1080P@59.94Hz 96: Custom1 97: Custom2 98: Custom3 99: Custom4	
0	1	26	0: Auto 1: HDMI 2: DVI	Output HDMI Type

Control Type		Function	Parameter	Description
Set	Get			
0	1	27	0: Best Fit 1: Letterbox 2: Follow Output 3: Virtual Wide 4: Follow Input 5: Custom	Aspect Ratio
0	1	28	-16 ~ 16	H-Pan
0	1	29	-16 ~ 16	V-Pan
0	1	30	-8 ~ 8	H-Zoom
0	1	31	-8 ~ 8	V-Zoom
0	1	32	0: 100% 1: 150% 2: 200% 3: 225% 4: 250% 5: 275% 6: 300% 7: 325% 8: 350% 9: 375% 10: 400% 11: Custom	Zoom
0	1	33	0 ~ 32	Custom Zoom
0	1	34	0 ~ 31	Zoom H-Pan
0	1	35	0 ~ 31	Zoom V-Pan

Control Type		Function	Parameter	Description
Set	Get			
0	1	36	0: Off 1: On	PIP On/Off
0	1	37	0: Picture-In-Picture 1: Picture + Picture 2: Split	PIP Type
0	1	38	0: Input 1 1: Input 2 2: Input 3 3: Input 4 4: VGA 1 5: VGA 2 6: HDMI 1 7: HDMI 2	PIP Source
0	1	39	0: 1/25 1: 1/16 2: 1/9 3: 1/4 4: Custom	PIP Size
0	1	40	0 ~ 128	PIP H-Position
0	1	41	0 ~ 128	PIP V-Position
0	1	42	0 ~ 255	PIP H-Size
0	1	43	0 ~ 255	PIP V-Size
0	1	44	0: Off 1: On	PIP Frame

Control Type		Function	Parameter	Description
Set	Get			
0	1	45	0: Red 1: Green 2: Blue	PIP Frame Color
0	1	46	0: Analog 1: S/PDIF	Audio Input Type
0	1	47	-22~0~+22	Audio Input Volume
0	1	48	-100~24	Audio Output Volume
0	-		111	Volume Up
0	-		-111	Volume Down
0	1	49	-36~0~+36	Audio Bass
0	1	50	-36~0~+36	Audio Treble
0	1	51	-10~10	Audio Balance
0	1	52	0: Off 1: On	Audio Loudness
0	1	53	0: Dynamic 1: User Define	Audio Delay
	1	54	0~340(step 2)	User Delay
0	1	55	0: No audio 1: Input 1 2: Input 2 3: Input 3 4: Input 4 5: VGA1 6: VGA2	Audio Input For USB

Control Type		Function	Parameter	Description
Set	Get			
0	1	56	0: Keystone 1: Anyplace 2: Rotation	Geometry Application
0	1	57	0: Front 1: Ceiling 2: Rear 3: Rear ceiling	Geometry Location
0	1	58	-40 ~ 40	Geometry Horizontal Keystone
0	1	59	-30~30	Geometry Vertical Keystone
0	1	60	-2000~2000	Geometry Diagonal Projection – Top Left H
0	1	61	-2000~2000	Geometry Diagonal Projection – Top Left V
0	1	62	-2000~2000	Geometry Diagonal Projection – Top Right H
0	1	63	-2000~2000	Geometry Diagonal Projection – Top Right V
0	1	64	-2000~2000	Geometry Diagonal Projection – Bottom Left H
0	1	65	-2000~2000	Geometry Diagonal Projection – Bottom Left V
0	1	66	-2000~2000	Geometry Diagonal Projection – Bottom Right H
0	1	67	-2000~2000	Geometry Diagonal Projection – Bottom Right V
0	-	68	n/a	Geometry Diagonal Projection – Reset
0	1	69	-20 ~ 20	Geometry Pincushion/Barrel
0	1	70	-180 ~ 180	Geometry Rotation
0	-	71	n/a	Geometry Reset all
0	-	72	0: Profile 1 1: Profile 2	Save Setting

Control Type		Function	Parameter	Description
Set	Get			
			2: Profile 3 3: Profile 4 4: Profile 5 5: Profile 6 6: Profile 7 7: Profile 8	
0	-	73	0: Profile 1 1: Profile 2 2: Profile 3 3: Profile 4 4: Profile 5 5: Profile 6 6: Profile 7 7: Profile 8	Recall Setting
0	1	74	0: Off 1: On	Frame Lock
0	-	75	n/a	Factory Reset
-	1	76	n/a	Firmware Revision
0	1	77	0: 1400x1050x60 1: 1680x1050x60	Mode Set – Mode 1
0	1	78	0: 1280x1024x75 1: 1280x1024x76	Mode Set – Mode 2
0	1	79	0: Center 1: Top Left 2: Top Right	OSD Menu Position

Control Type		Function	Parameter	Description
Set	Get			
			3: Bottom Left 4: Bottom Right	
0	1	80	0: 5 sec 1: 10 sec 2: 20 sec 3: 30 sec 4: 60 sec 5: 90 sec 6: Off	OSD Time Out
0	1	81	0: Off 1: On 2: Custom	Logo
0	1	82	0: Black 1: Blue	Blank Color
0	-	83	n/a	Capture
0	1	84	0: Black 1: Blue 2: Custom 3: Disable Analog Sync	Background
0	1	85	0: Off 1: On	Save Lock
0	1	86	0: Off 1: On	Input Lock
0	1	87	0: Blank & Mute 1: Blank	Blank key function



Control Type		Function	Parameter	Description
Set	Get			
			2: Mute	
0	1	88	0: Freeze & Mute 1: Freeze 2: Mute	Freeze key function
0	1	89	0: Off 1: On	Freeze
0	1	90	0: Off 1: On	Blank
0	1	91	0: Off 1: On	Power
0	-	92	n/a	Info
0	-	93	n/a	Menu
0	-	94	n/a	Top
0	-	95	n/a	Down
0	-	96	n/a	Left
0	-	97	n/a	Right
0	-	98	n/a	Enter
0	-	99	n/a	Picture
0	-	100	n/a	Swap
0	1	101	0: Off 1: On	Mute

Control Type		Function	Parameter	Description
Set	Get			
0	1	102	0: Off 1: On	Lock
-	1	103	0: 640x480      60 1: 640x480      67    Mac13 2: 640x480      72 3: 640x480      75 4: 640x480      85 5: 720x400      70 6: 720x400      85 7: 800x600      56 8: 800x600      60 9: 800x600      72 10: 800x600      75 11: 800x600      85 12: 832x624      75    Mac16 13: 1024x768      60 14: 1024x768      70 15: 1024x768      75 16: 1024x768      75    Mac19 17: 1024x768      85 18: 1024x800      84    Sun 19: 1152x864      75 20: 1152x870      75    Mac21 21: 1152x900      66    Sun 22: 1152x900      76    Sun	Main Input status

Control Type		Function	Parameter	Description
Set	Get			
			23: 1280x960 60	
			24: 1280x960 85	
			25: 1280x768 60	
			26: 1280x1024 60	
			27: 1280x1024 75	
			28: 1280x1024 76 Sun	
			29: 1280x1024 85	
			30: 1400x1050 60	
			31: 1400x1050 75	
			32: 1600x1200 60	
			33: 1680x1050 60	
			34: 1080i 60	
			35: 1080i 50	
			36: 1080p 60	
			37: 1080p 50	
			38: 720p60 60	
			39: 720p50 50	
			40: 480i	
			41: 480p	
			42: 576i	
			43: 576p	
			44: 1280x800 60(Reduce blank)	
			45: 1920x1200 60	
			46: 1920x1080 60	
			47: 1280x720 60	

Control Type		Function	Parameter	Description
Set	Get			
			48: 1080p 24 49: 1280x800 60 50: 1440x900 60 51: 1440x900 60(Reduce blank) 52: 1280x768_60 (Reduce blank) 53: 1680x1050 60(Reduce blank) 54: 1366x768 60 55: 1366x768_60 (Reduce blank) 94: Custom1 95: Custom2 96: Custom3 97: Custom4 98: No Input detected 99: other 101: NTSC 102: PAL 103: PAL-M 104: PAL-N 105: NTSC 4.43 106: SECAM 107: PAL-60	

Control Type		Function	Parameter	Description
Set	Get			
-	1	104	0: 640x480 60 1: 640x480 67 Mac13 2: 640x480 72 3: 640x480 75 4: 640x480 85 5: 720x400 70 6: 720x400 85 7: 800x600 56 8: 800x600 60 9: 800x600 72 10: 800x600 75 11: 800x600 85 12: 832x624 75 Mac16 13: 1024x768 60 14: 1024x768 70 15: 1024x768 75 16: 1024x768 75 Mac19 17: 1024x768 85 18: 1024x800 84 Sun 19: 1152x864 75 20: 1152x870 75 Mac21 21: 1152x900 66 Sun 22: 1152x900 76 Sun 23: 1280x960 60 24: 1280x960 85	PIP Input status

Control Type		Function	Parameter	Description
Set	Get			
			25: 1280x768 60	
			26: 1280x1024 60	
			27: 1280x1024 75	
			28: 1280x1024 76 Sun	
			29: 1280x1024 85	
			30: 1400x1050 60	
			31: 1400x1050 75	
			32: 1600x1200 60	
			33: 1680x1050 60	
			34: 1080i 60	
			35: 1080i 50	
			36: 1080p 60	
			37: 1080p 50	
			38: 720p60	
			39: 720p50	
			40: 480i	
			41: 480p	
			42: 576i	
			43: 576p	
			44: 1280x800 60(Reduce blank)	
			45: 1920x1200 60	
			46: 1920x1080 60	
			47: 1280x720 60	
			48: 1080p 24	
			49: 1280x800 60	

Control Type		Function	Parameter	Description
Set	Get			
			50: 1440x900 60 51: 1440x900 60(Reduce blank) 52: 1280x768_60 (Reduce blank) 53: 1680x1050 60(Reduce blank) 54: 1366x768 60 55: 1366x768_60 (Reduce blank) 94: Custom1 95: Custom2 96: Custom3 97: Custom4 98: No Input detected 99: other 101: NTSC 102: PAL 103: PAL-M 104: PAL-N 105: NTSC 4.43 106: SECAM 107: PAL-60	
0	1	105	512~3071	Advance Input Mode: HT

Control Type		Function	Parameter	Description
Set	Get			
0	1	106	32~(HS-48)	Advance Input Mode: HW
0	1	107	80~(HT-HA-12)	Advance Input Mode: HS
0	1	108	640~1920 <= (HT-92)	Advance Input Mode: HA
0	1	109	0: Negative polarity 1: Positive polarity	Advance Input Mode: HP



Control Type		Function	Parameter	Description
Set	Get			
0	1	110	384~2047	Advance Input Mode: VT
0	1	111	2~(HS-13)	Advance Input Mode: VW
0	1	112	15~(VT-VA-1)	Advance Input Mode: VS
0	1	113	480~1200 <= (VT-16)	Advance Input Mode: VA

Control Type		Function	Parameter	Description
Set	Get			
0	1	114	0: Negative polarity 1: Positive polarity	Advance Input Mode: VP
0	1	115	25 < OCLK < 165	Advance Input Mode: OCLK(Integer)
0	1	116	25 < OCLK < 165	Advance Input Mode: OCLK(Decimal)
0	1	117	0: Off 1: On	Advance Input Mode: Enable

Control Type		Function	Parameter	Description
Set	Get			
0	-	118	n/a	Advance Input Mode: Save
0	1	119	512~3071	Advance Output Mode: HT
0	1	120	32~(HS-48)	Advance Output Mode: HW
0	1	121	80~(HT-HA-12)	Advance Output Mode: HS

Control Type		Function	Parameter	Description
Set	Get			
0	1	122	640~1920 <= (HT-92)	Advance Output Mode: HA
0	1	123	0: Negative polarity 1: Positive polarity	Advance Output Mode: HP
0	1	124	384~2047	Advance Output Mode: VT
0	1	125	2~(HS-13)	Advance Output Mode: VW

Control Type		Function	Parameter	Description
Set	Get			
0	1	126	15~(VT-VA-1)	Advance Output Mode: VS
0	1	127	480~1200 ≤ (VT-16)	Advance Output Mode: VA
0	1	128	0: Negative polarity 1: Positive polarity	Advance Output Mode: VP
0	1	129	25 < OCLK < 165	Advance Output Mode: OCLK(Integer)

Control Type		Function	Parameter	Description
Set	Get			
0	1	130	25 < OCLK < 165	Advance Output Mode: OCLK(Decimal)
0	-	131	n/a	Advance Output Mode: Save
0	-	132	n/a	Advance Output Mode: Set Current
0	-	133	n/a	Volume Up
0	-	134	n/a	Volume Down
0	1	135	0: Follow Output 1: Follow Input	HDCP Setting
0	1	136	0:Custom1 1:Custom2 2:Custom3 3:Custom4	Advance Input Mode: Custom Input

Control Type		Function	Parameter	Description
Set	Get			
0	1	137	0:Custom1 1:Custom2 2:Custom3 3:Custom4	Advance Output Mode: Custom Output
0	1	138	0: Off 1: On	Overscan
0	1	139	0: Seamless 1: Fast	Switching Mode
0	1	140	0: Manual 1: Auto	Auto Image Mode
0	-	141	n/a	Slideshow Start
0	-	142	n/a	Slideshow Stop
0	-	143	n/a	Slideshow Pause
0	-	144	n/a	Slideshow Next
0	-	145	n/a	Slideshow Previous

Control Type		Function	Parameter	Description
Set	Get			
0	1	146	0: Min 1: Low 2: Mid 3: Long 4: Max 5: Off	Slideshow
0	1	147	0: 1280x768x60 1: 1366x768x60	Mode Set – Mode 3
0	1	148	0 : Off 1 : On	HDMI1 Hot Plug
0	1	149	0 : Off 1 : On	HDMI2 Hot Plug
0	1	150	0 : Input 1 1 : Input 2 2 : Input 3 3 : Input 4 4 : VGA 1 5 : VGA 2 6 : HDMI 1	HDMI1 Audio Input
0	1	151	0 : Input 1 1 : Input 2 2 : Input 3 3 : Input 4 4 : VGA 1	HDMI2Audio Input



Control Type		Function	Parameter	Description
Set	Get			
			5 : VGA 2 6 : HDMI 2	
0	-	152	-	Custom Output Read HDMI EDID Prefer Timing
0	1	153	0 : Off 1 : On	HDMI1 Input HDCP On/Off
0	1	154	0 : Off 1 : On	HDMI2Input HDCP On/Off

#### 4 Error Code

Error code	Description
ERR 1	Unknown command
ERR 2	Unknown function
ERR 3	Unavailable function
ERR 4	Unknown control type
ERR 5	Unavailable get function
ERR 6	Unavailable set function
ERR 7	Unavailable parameter
ERR 8	Too few arguments